

Downloading ebooks to your Sony eReader or Nook

1. On our website, click on the link to OverDrive, which is located halfway down the home page on the left side. Or, visit www.omnilibraries.org. This is the home page of OMNI Libraries, which is the consortium we belong to.
2. On the left side of the page, scroll down to Adobe Digital Editions and click on the link.
 - a. Click on the button “Get Adobe Digital Editions,” click “download now,” click “Install” and follow the rest of the installation prompts.
 - b. *Note - Once installed a window will pop up asking which components you would like installed. I would recommend leaving the boxes checked as is and click “next.”
3. You will now see the Set-up assistant. Click “Continue.” At this point, you will need to register for an Adobe ID. This is free and very easy. Click “Get an Adobe ID online.”
 - a. You will be taken to a webpage. Click on “Get Adobe Account.” You will now be prompted to create your account. Enter in your e-mail address, choose a password, and enter in any information with an astrick (*) next to it. This is required.
 - b. *Note – Remember the email address and password you chose – you will need it again.R
4. Returning to the set-up assistant, enter in your email and password to authorize your computer.
5. Now that the software set-up is complete, return to the OMNI website to browse for books or search for a specific title.
 - a. Browse by selecting eBook Fiction or eBook Nonfiction from the left side. Hover over the category for a list of different genres (mystery & suspense, historical, romance, etc.)
 - b. Search for a specific author or title by using the search bar at the top of the screen, or selecting advanced search.
 - c. *Note – Select “Only show titles with copies available” to limit your search. If a title only allows you to “place a hold,” it is checked out and unavailable. If you have the “add to cart” option, you can check out the title.
 - d. *Note – Be aware of the format. EPUB & PDF are for ebooks. MP3 and WMA are for audiobooks. See a separate guide for instructions on Kindle books.
6. Click on the title to find out more information about the ebook including descriptions and readalikes. If this is the title you would like to check-out, click on “Add to cart.”
 - a. *Note - Make sure you select either the Adobe EPUB ebook or Adobe PDF ebook, NOT the Kindle.
7. Once added to your cart, you can either continue browsing for more books or check-out.
8. Once you proceed to checkout, you will have the option to choose your lending period. eBooks can be returned early, and you can only have 3 checked out at one time. If you do not have the chance to return the item early, it will automatically be returned at the end of the lending period. Click “Confirm Check Out.”
9. Click “Download.” You will get a pop-up window. Leave it selected to “Open with Adobe Digital Editions” and click “ok.”

10. The book will open up in Adobe Digital Editions. This is the reading view. You can read the book from your computer, if you would like!
11. To transfer to your ebook reader, click on the Library View icon, which is at the top left of the screen. It will look like the spines of three books. If you hover over the icons, text will appear to show you which is the Library View and which is the Reading View.
12. Turn on your ereader and plug it into your computer. You should get a pop-up asking you to log in with your Adobe ID. Enter in your email and password you chose to authorize your ereader. Once that is done, you should notice a listing for your ereader on the left side of the screen under Recently Read.
13. Simply click on the book and drag it so it is hovering over the ereader listing. Drop it. The ebook should load in a matter of seconds onto your ereader. To access the book on your ereader, unplug from the computer and look under “My Bookshelf” or “My Documents.” Every ereader is different, so it might be stored somewhere not expected. Look around your ereader—it should be there somewhere.
14. To return a book early, simply click on the tiny arrow that is located in the top left corner of the book. A drop-down should open—the last option is “Return Borrowed Book.” Follow the prompts to return it and you should regain a check-out credit. Once returned, the book usually deletes itself off your ereader in about 24 hours.
 - a. *Note – When returning items early* - if you return several books within a short time frame, your account may be locked. It can take 4-7 days to unlock an account. **WE ARE NOT RESPONSIBLE FOR LOCKING OR UNLOCKING ACCOUNTS.** To avoid this, space out your returns if you have more than one, and/or space out your returns from your new checkouts.

One last thing:

If you are not getting a prompt to authorize your device (i.e. you are unable to register your Nook with your Adobe ID and password), try these steps.

1. Exit Adobe Digital Editions
2. Plug in the Nook and relaunch Adobe Digital Editions
3. Hopefully the Authorize Device Assistant will open up and you will be prompted to register.

If not.....

1. Exit Adobe Digital Editions
2. Plug in the Nook to the computer
3. Open up the removable drive that the Nook is hooked up to (normally My Computer --> E or F drive (should say Nook).
4. Delete any folders associated with Adobe Digital Editions. I have only come across two: Digital Editions and .adobe-digital-editions.
5. Unplug the Nook and plug it back in and check to make sure those folders have been deleted.
6. Launch Adobe Digital Editions -- this time you should get the set-up assistant.

Questions:

Still have questions? Call us at 815-725-1715 and ask for the reference department and we can help. Or, feel free to email us at reference@shorewoodtroylibrary.org with your name, library card number, the problem you are encountering, the exact text of any error messages, and a phone number to reach you at.